

POCKET REFERENCE

VISICALC[®]

FOR THE TRS-80[®] MODEL 4

Program Created and Written by
Software Arts Products Corp.

Manufactured for


Radio Shack[®]
A DIVISION OF TANDY CORPORATION



VISICORP[™]

Exclusive Distributor

A VISICALC® SCREEN



The screenshot displays a spreadsheet interface with several cells containing different types of data and formulas:

- C1:** Contains the formula `=C17`.
- C17:** Contains the value `17`.
- J1:** Formula cell containing `=Rate`.
- J2:** Formula cell containing `=NPV`.
- Range J3:L4:** Formula cell containing `=SUM(J3:L3)`.
- Range J5:L8:** Data range containing values: 767, 3173; 920, 3608; 736, 2951; 95, 495; 89, 242.
- Range J9:L15:** Data range containing years from 1981 to 1987 and corresponding growth rates: 1981 (**), 1982 (*), 1983 (*), 1984 (**), 1985 (***)+, 1986 (****)+, 1987 (*****)+.

Recalculation Order Indicator:
If R, across rows.
If C, down columns.
If ! is present, sheet is being recalculated.

Memory Indicator:
How many K memory available.
If OM, out of room.

Left-aligned Format (/FL)

General Format (/FG)

Repeating Label (/ -)

Value

Graph Format (/F*)

Integer Format (/FI)

Right-aligned Format (/FR)

USE OF KEYS

MOVING THE CURSOR

→ ← ↑ ↓	Move the cursor in the designated direction. Used in value entry and some commands to point to an entry position that will be selected when [ENTER] or a colon is pressed. Move edit cue in Edit Command (see /E).
;	Moves cursor between windows (see /W).
>coord	Go To Command. Cursor moves to designated coordinate.
[F1]	Moves cursor to upper-left corner of worksheet.

CALCULATING

+	Addition
-	Subtraction
*	Multiplication
/	Division
[CLEAR] ;	Exponentiation
#	If the coordinate is immediately to left of edit cue, replaces coordinate with that location's current value. Otherwise places current value of cursor location on edit line.
!	When the edit line is clear, forces recalculation of entire sheet. When formula is on the edit line, replaces formula on edit line with its current value.

EDITING

[F2]	Deletes character to left of edit cue on edit line. If edit cue is at beginning of edit line, cancels command entry and clears prompt line.
[CTRL]-C	Cancels command, clearing edit line and prompt line; stops printing or disk storage operation in progress.
[F3]	Invokes Edit Command during entry on the edit line (see /E).

LABELS

Start with any letter or ““. The initial quotation mark does not appear on the edit line. Defines the entry as a label with the numeric value of zero. Labels are left-aligned in the entry position. Correct typing errors while entering with [F2] or [F3].

VALUES

Start with a digit (0 through 9), plus (+), minus (-), open parenthesis, period (.), number sign (#), or at sign (@). In General format, program shifts between conventional and scientific notation as required to display the calculated value to the greatest precision. If column is too narrow to display the number in scientific notation, greater-than signs (>) fill the entry position.

VALUE REFERENCES

Entry position coordinate used as element in a formula. Value references are allowed wherever numbers are allowed. To start a value entry with a value reference, begin with + .

FILE NAMES

A file name can be given in the VisiCalc program by:

- Typing the entire file name for the file.
- Scrolling the name from the current directory with the → .
- Typing a drive designator (e.g., :1) and pressing [ENTER], then scrolling file names with the → .

A file name may be edited before pressing [ENTER] by:

- Using the [F2] key to delete single characters.
- Typing additional characters to add to the name.
- Using [F3] to edit the file name.

FUNCTIONS

Provide common formulas for use in values. Each function begins with @ followed by the name of the function; most functions also require an expression in parentheses (the argument). An argument includes the values (formulas and numbers) upon which the function calculates.

The arguments may be:

<i>v</i>	Any valid VisiCalc value.
<i>l</i>	Any logical value.
<i>list</i>	Any combination of values and ranges separated by commas.
<i>range</i>	A portion of a row or column specified by its beginning coordinate, a period (displayed as an ellipsis), and its final coordinate.
@ABS(<i>v</i>)	Absolute value of <i>v</i> .
@AVERAGE(<i>list</i>)	Average of the non-blank entries in <i>list</i> . Maximum of 255 entries in <i>list</i> .
@COUNT(<i>list</i>)	Number of non-blank entries in <i>list</i> . Maximum of 255 entries in <i>list</i> .
@EXP(<i>v</i>)	Natural exponent of <i>v</i> .
@INT(<i>v</i>)	Integer portion of <i>v</i> .
@LN(<i>v</i>)	Natural logarithm of <i>v</i> .
@LOG10(<i>v</i>)	Base 10 logarithm of <i>v</i> .
@MAX(<i>list</i>)	Maximum value in <i>list</i> .
@MIN(<i>list</i>)	Minimum value in <i>list</i> .
@NPV (<i>dr</i> , <i>range</i>)	Net present value of the cash flow in <i>range</i> , discounted at the rate specified in the expression <i>dr</i> (discount rate).
@SQRT(<i>v</i>)	Square root of <i>v</i> .
@SUM(<i>list</i>)	Sum of the values in <i>list</i> .

TRIGONOMETRIC FUNCTIONS

All angles are in radians.

@SIN(<i>v</i>)	Sine of <i>v</i> .
@COS(<i>v</i>)	Cosine of <i>v</i> .
@TAN(<i>v</i>)	Tangent of <i>v</i> .
@ASIN(<i>v</i>)	Arcsine of <i>v</i> .
@ACOS(<i>v</i>)	Arccosine of <i>v</i> .
@ATAN(<i>v</i>)	Arctangent of <i>v</i> .

SEARCH FUNCTIONS

@CHOOSE (<i>v</i> , <i>list</i>)	Returns the <i>v</i> th element of <i>list</i> . If <i>v</i> is 0 or greater than the number of elements in <i>list</i> , NA is returned.
@LOOKUP (<i>v</i> , <i>range</i>)	Compares <i>v</i> to the successive values in <i>range</i> and returns the corresponding value from the column or row immediately to the right or below the entries in <i>range</i> .

FUNCTIONS WITHOUT ARGUMENTS

@ERROR	Makes all expressions referencing the value display ERROR.
@FALSE	Logical value FALSE.
@NA	Makes all expressions referencing the value display NA.
@PI	3.1415926536.
@TRUE	Logical value TRUE.

LOGIC FUNCTIONS

@AND(<i>list</i>)	TRUE if all values in <i>list</i> are TRUE, otherwise FALSE.
@OR(<i>list</i>)	TRUE if any value in <i>list</i> is TRUE, otherwise FALSE.
@NOT (<i>l</i>)	TRUE if <i>l</i> is FALSE, FALSE if <i>l</i> is TRUE.
@IF(<i>l</i> , <i>v1</i> , <i>v2</i>)	<i>v1</i> if <i>l</i> is TRUE, <i>v2</i> if <i>l</i> is FALSE.
@ISERROR(<i>v</i>)	TRUE if <i>v</i> is ERROR, otherwise FALSE.
@ISNA(<i>v</i>)	TRUE if <i>v</i> is NA, otherwise FALSE.

LOGICAL OPERATORS

<, >, = <=	Compares two numeric values and results in either the logical value TRUE or FALSE.
<>	

COMMANDS

/B	Blank	Erases the highlighted entry position. [ENTER] or arrow key completes command.
/C	Clear	Clears the worksheet, restores the General format and single window. Y completes command, any other key cancels.
/D	Delete	Deletes the entire row (/DR) or column (/DC) on which the cursor rests.
/E	Edit	Allows editing of entry position contents. Places the contents of the highlighted entry position on the edit line. The left and right arrow keys (\uparrow and \downarrow) move the edit cue over the characters without changing them. Delete to the left of the edit cue with the [F2] key. Enter to the left of the edit cue by typing characters. [F3] invokes the Edit Command while entering values, labels, and file names.
/F	Format	Sets local format for the highlighted entry position but does not affect contents in memory. Remains until changed or the worksheet is cleared.
/FD	Default	Resets to the global format.
/FG	General	Maximum precision.
/FI		Integer.
/FL		Left-aligned.
/FR		Right-aligned.
/F\$		Dollars-and-cents (two decimal places).
/F*	Graph	Replaces value with asterisks equal to its integer value.
/G	Global	Affects entire window or sheet.
/GC	Column	Sets column width of all columns to specified number (3 to 77). [ENTER] completes command.
/GO	Order of Recalculation	Specifies whether the worksheet is to be recalculated down the columns (/GOC) or across the rows (/GOR).
/GR	Recalculation priority	Sets recalculation to automatic (/GRA) or manual (/GRM). Typing ! causes recalculation.

/GF	Format	Sets display format for all columns not specifically formatted. See /F for format specifications.
/I	Insert	Inserts a new blank row (/IR) or column (/IC) at the cursor position.
/M	Move	Moves an entire row or column to another position on the sheet. The first coordinate on the edit line designates the row or column to be moved. The final coordinate specifies where the row or column is to be moved. [ENTER] completes command.
/P		See "Printing."
/-	Repeating Label	Fills the entry position with the designated character(s).
/R		See "Replicating."
/S		See "Storing."
/T	Titles	Fixes rows and columns in place on the screen so they remain in view when the window is scrolled. The position of the cursor determines which column(s) and/or row(s) are to be fixed. The Go To command (>) moves the cursor into a fixed area.
/TH	Horizontal	Fixes rows at and above the cursor.
/TV	Vertical	Fixes columns at and to the left of the cursor.
/TB	Both	Fixes columns and rows.
/TN	None	Unfixes all rows and columns.
/V	Version	Displays the copyright notice and version number.
/W	Window	Splits the screen vertically or horizontally at the current cursor position. The semicolon (;) moves the cursor from one window to the other. Global commands affect only the window containing the cursor.
/WH	Horizontal	Splits the screen just above the row with the cursor.
/WV	Vertical	Splits the screen just to the left of the column with the cursor.
/WS	Synchronized scrolling	Split windows scroll together.
/WU	Unsynchronized scrolling	Cancels synchronized scrolling.

PRINTING

The Print command sends a contiguous rectangular portion of the worksheet to a printer or to diskette. Formulas are not sent (to print formulas and formats, see /SS). To print all or part of a VisiCalc sheet:

1. Place the cursor on the upper-left coordinate of the rectangular area to be printed and type /P.
2. Type F to send to diskette file. Type P to send to a printer.
3. To send setup strings, type "", the strings, then [ENTER]. The following special characters can be used:
 - [CLEAR]; C *char* Sends next character as a control character.
 - [CLEAR]; E Sends the Escape character.
 - [CLEAR]; H*nn* Sends the single ASCII character defined by the hexadecimal digits nn.
 - [CLEAR]; R Sends a return character.
 - [CLEAR]; L Sends a line feed character.
 - [CLEAR]; [CLEAR]; Sends one caret character (^).

The setup strings must be reentered each time the Print command is used. Invalid setup strings sent to the printer give no error indication.

4. Enter lower-right coordinate of the rectangle to be printed, either by typing it or pointing the cursor to it, and press [ENTER].

REPLICATING

The Replicate command copies the entry contents of the source range (the position(s) to be copied) into the target range (the position(s) to which it will be copied.)

A range is a portion of a row or column specified by its beginning coordinate, a period (shown as ...), and its final coordinate.

A colon separates the source range from the target range and is entered by typing either colon or [ENTER].

	Source	Target
To copy one entry once	coordinate	: coordinate
To copy one entry several times	coordinate	: range in one row or column
To copy a row or column once	row or column range	: starting coordinate
To copy a row several times	row range	: range in one column
To copy a column several times	column range	: range in one row

[ENTER] completes command.

If the source range includes reference to other locations, indicate how each reference is to be treated:

N	No Change	Copies the reference as it appears in the source entry.
R	Relative	Changes the reference so that it is relative to the target position.

STORING

The Storage command writes a file to diskette, reads a saved file from diskette, writes and reads files in the DIF™ format, deletes files from a diskette, initializes diskettes, and quits the VisiCalc program. File names can be displayed from the diskette by pressing the right arrow key when prompted for the file name.

/SL	Load	Reads a file previously saved with /SS. The file is loaded over the current sheet. New entries replace old ones. Any entries that are not replaced remain the same. To load a file into an empty worksheet, clear with /C before loading new file.
/SS	Save	Saves the information on the worksheet on diskette under the specified file name. To print out formulas and formats, type /SS: PR.
/SD	Delete file	Deletes the specified file from the diskette.
/SQ	Quit	Quits the VisiCalc program, allowing booting of another program diskette.
/SE	Execute TRSDOS command	Allows entry of TRSDOS command and returns to the worksheet.
/S#S		Writes the specified area of worksheet to diskette as a file in the DIF™ format. R or [ENTER] saves by rows, C saves by columns.
/S#L		Loads a file in the DIF™ format. R or [ENTER] loads the information by rows, C loads by columns.

Copyright © 1983 VisiCorp
Printed in U.S.A.
All Rights Reserved.

VisiCalc Program Copyright © 1979, 1983 Software Arts Products Corp.
All Rights Reserved.

DIF™ is a trademark of Software

Arts Products Corp.

TRSDOS® is a registered trademark of Tandy Corporation

TRS-80® is a registered trademark of Tandy Corporation

VisiCalc® is a registered trademark of VisiCorp